Bioscara

Generated by Doxygen 1.9.8

1 Documentation	1
2 Todo List	3
3 Class Index	5
3.1 Class List	5
4 File Index	7
4.1 File List	7
5 Class Documentation	9
5.1 Gripper Class Reference	9
5.1.1 Detailed Description	10
5.1.2 Constructor & Destructor Documentation	10
5.1.2.1 Gripper()	10
5.1.3 Member Function Documentation	10
5.1.3.1 deinit()	10
5.1.3.2 disable()	10
5.1.3.3 enable()	11
5.1.3.4 init()	11
5.1.3.5 setPosition()	11
5.1.4 Member Data Documentation	11
5.1.4.1 pwm	11
5.2 Joint Class Reference	12
5.2.1 Detailed Description	13
5.2.2 Member Enumeration Documentation	14
5.2.2.1 stp_reg_t	14
5.2.3 Constructor & Destructor Documentation	15
5.2.3.1 Joint()	15
5.2.4 Member Function Documentation	15
5.2.4.1 checkCom()	15
5.2.4.2 checkOrientation()	15
5.2.4.3 deinit()	15
5.2.4.4 disable()	15
5.2.4.5 disableCL()	15
5.2.4.6 enable()	15
5.2.4.7 enableStallguard()	16
5.2.4.8 getFlags()	16
5.2.4.9 getIsHomed() [1/2]	16
5.2.4.10 getIsHomed() [2/2]	17
5.2.4.11 getIsSetup() [1/2]	17
5.2.4.12 getIsSetup() [2/2]	17
5.2.4.13 getPosition()	17
5.2.4.14 getStall()	17

5.2.4.15 getVelocity()	18
5.2.4.16 home()	18
5.2.4.17 init()	18
5.2.4.18 isHomed()	18
5.2.4.19 isSetup()	19
5.2.4.20 moveSteps()	19
5.2.4.21 printlnfo()	19
5.2.4.22 read()	19
5.2.4.23 setBrakeMode()	20
5.2.4.24 setDriveCurrent()	20
5.2.4.25 setHoldCurrent()	20
5.2.4.26 setPosition()	21
5.2.4.27 setVelocity()	21
5.2.4.28 stop()	21
5.2.4.29 write()	21
5.2.5 Member Data Documentation	22
5.2.5.1 address	22
5.2.5.2 flags	22
5.2.5.3 gearRatio	23
5.2.5.4 handle	23
5.2.5.5 ishomed	23
5.2.5.6 issetup	23
5.2.5.7 name	23
5.2.5.8 offset	23
	24
5.3.1 Detailed Description	25
5.3.2 Constructor & Destructor Documentation	25
5.3.2.1 Joint_comms()	25
$5.3.2.2 \sim \text{Joint_comms}() \dots \dots$	25
5.3.3 Member Function Documentation	25
5.3.3.1 addJoint()	25
5.3.3.2 checkOrientations() [1/2]	26
5.3.3.3 checkOrientations() [2/2]	26
5.3.3.4 deinit()	26
5.3.3.5 disableCLs()	27
5.3.3.6 disables()	27
5.3.3.7 enables() [1/2]	27
5.3.3.8 enables() [2/2]	27
5.3.3.9 enableStallguards()	28
5.3.3.10 getPositions()	28
5.3.3.11 getVelocities()	29
5.3.3.12 home()	29

5.3.3.13 init()	 	29
5.3.3.14 setBrakeModes()	 	30
5.3.3.15 setDriveCurrents() [1/2]	 	30
5.3.3.16 setDriveCurrents() [2/2]	 	30
5.3.3.17 setHoldCurrents() [1/2]	 	31
5.3.3.18 setHoldCurrents() [2/2]	 	31
5.3.3.19 setPositions()	 	32
5.3.3.20 setVelocities()	 	32
5.3.3.21 stops()	 	32
5.3.4 Member Data Documentation	 	33
5.3.4.1 joints	 	33
5.4 RPI_PWM Class Reference	 	33
5.4.1 Detailed Description	 	34
5.4.2 Constructor & Destructor Documentation	 	34
5.4.2.1 ~RPI_PWM()	 	34
5.4.3 Member Function Documentation	 	34
5.4.3.1 disable()	 	34
5.4.3.2 enable()	 	34
5.4.3.3 setDutyCycle()	 	34
5.4.3.4 setDutyCycleNS()	 	34
5.4.3.5 setPeriod()	 	34
5.4.3.6 start()	 	35
5.4.3.7 stop()	 	35
5.4.3.8 writeSYS()	 	35
5.4.4 Member Data Documentation	 	35
5.4.4.1 chippath	 	35
5.4.4.2 per	 	35
5.4.4.3 pwmpath	 	35
File Documentation		37
6.1 Arduino/joint/configuration.h File Reference		37 37
6.1.1 Detailed Description		38
6.1.2 Macro Definition Documentation		38
6.1.2.1 ADR		38
6.1.2.2 MAXACCEL		38
6.1.2.3 MAXVEL		38
6.2 configuration.h		39
6.3 Arduino/joint/joint.h File Reference		39
6.3.1 Detailed Description		39 41
6.3.2 Macro Definition Documentation		41
6.3.2.1 ACK		41
6.3.2.2 DUMP BUFFER	 	41

6

6.3.2.3 MAX_BUFFER	42
6.3.2.4 NACK	42
6.3.2.5 RFLAGS_SIZE	42
6.3.3 Enumeration Type Documentation	42
6.3.3.1 stp_reg_t	42
6.3.4 Function Documentation	43
6.3.4.1 readValue()	43
6.3.4.2 writeValue()	43
6.4 joint.h	44
6.5 Arduino/joint/joint.ino File Reference	45
6.5.1 Detailed Description	46
6.5.2 Macro Definition Documentation	46
6.5.2.1 J4	46
6.5.3 Function Documentation	47
6.5.3.1 loop()	47
6.5.3.2 receiveEvent()	47
6.5.3.3 requestEvent()	47
6.5.3.4 setup()	48
6.5.3.5 stepper_receive_handler()	48
6.5.3.6 stepper_request_handler()	48
6.5.4 Variable Documentation	48
6.5.4.1 reg	48
6.5.4.2 rx_buf	49
6.5.4.3 rx_data_ready	49
6.5.4.4 rx_length	49
6.5.4.5 stepper	49
6.5.4.6 tx_buf	49
6.5.4.7 tx_data_ready	49
6.5.4.8 tx_length	49
6.6 docs/DOCS_README.md File Reference	49
6.7 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/common.h File Reference	49
6.7.1 Detailed Description	50
6.7.2 Macro Definition Documentation	51
6.7.2.1 DUMP_BUFFER	51
6.8 common.h	51
6.9 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mGripper.h File Reference	51
6.9.1 Detailed Description	52
6.10 mGripper.h	53
6.11 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.h File Reference	53
6.11.1 Detailed Description	55
6.11.2 Macro Definition Documentation	55
6.11.2.1 ENCODERS IOINTANGLE	55

6.11.2.2 JOINT2ENCODERANGLE	55
6.12 mJoint.h	55
6.13 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.hpp File Reference	E 7
ence	57
6.13.1 Detailed Description	58
6.14 mJoint.hpp	59
6.15 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJointCom.h File Reference	59
6.15.1 Detailed Description	60
6.16 mJointCom.h	61
6.17 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/ul2C.h File Reference .	62
6.17.1 Detailed Description	64
6.17.2 Macro Definition Documentation	64
6.17.2.1 ACK	64
6.17.2.2 MAX_BUFFER	64
6.17.2.3 NACK	64
6.17.2.4 RFLAGS_SIZE	65
6.17.3 Function Documentation	65
6.17.3.1 closel2CDevHandle()	65
6.17.3.2 openI2CDevHandle()	65
6.17.3.3 readFromI2CDev()	65
6.17.3.4 writeToI2CDev()	66
6.18 ul2C.h	66
6.19 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/uPWM.h File Reference	67
6.19.1 Detailed Description	68
6.20 uPWM.h	69
6.21 ROS2/ros2_scara_ws/src/joint_communication/src/joint_comm_node.cpp File Reference	70
6.21.1 Function Documentation	70
6.21.1.1 INT_handler()	70
6.21.1.2 main()	71
6.21.2 Variable Documentation	71
6.21.2.1 _Gripper	71
6.21.2.2 _Joints	71
6.22 ROS2/ros2_scara_ws/src/joint_communication/src/mGripper.cpp File Reference	71
6.23 ROS2/ros2_scara_ws/src/joint_communication/src/mJoint.cpp File Reference	72
6.24 ROS2/ros2_scara_ws/src/joint_communication/src/mJointCom.cpp File Reference	72
6.25 ROS2/ros2_scara_ws/src/joint_communication/src/ul2C.cpp File Reference	73
6.25.1 Function Documentation	74
6.25.1.1 closeI2CDevHandle()	74
6.25.1.2 openI2CDevHandle()	74
6.25.1.3 readFromI2CDev()	74
6.25.1.4 writeToI2CDev()	76

Index 77

Chapter 1

Documentation

This documentation currently documents the following:

- The joint firmware in the \slash Arduino directory
- The interfacing library used for communicating with the joins in the /ROS2 directory.

2 Documentation

Chapter 2

Todo List

Member Joint::read (const stp_reg_t reg, T &data, u_int8_t &flags)

Implement a return code for read only functions

· Implement clearStall function

Member Joint_comms::addJoint (const int address, const std::string name, const float gearRatio, const int offset)

Measure joint ranges

· Investigate if possible to make independent of homing

Member Joint_comms::checkOrientations (std::vector< float > angle_v)

Only execute if not performed before

• save in private flag and inhibit movement if this has not been executed.

Member loop (void)

why are BIT2 and BIT3 constantly checked and set? Would it be sufficient to do this only invoking the actual functions?

4 Todo List

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Gripper		
	Gripper object to interact with the robot gripper	9
Joint		
	Representing a single joint on the I2C bus	12
Joint_coi	mms	
	Communication object for all joints	24
RPI_PW	'M	
	PWM class for the Raspberry PI 4 and 5	33

6 Class Index

Chapter 4

File Index

4.1 File List

Here is a list of all files with brief descriptions:

Arduino/joint/configuration.h	
Configuration definitions for Joint 1 to Joint 4	37
Arduino/joint/joint.h	
Joint firmware header	39
Arduino/joint/joint.ino	
Joint firmware	45
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/common.h	
A file containing utility macros and functions	49
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mGripper.h	
File containing the Gripper class	51
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.h	
File including the Joint class	53
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.hpp	
Templated functions for the Joint class	57
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJointCom.h	
File containing the Joint_comms class	59
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/ul2C.h	
Low level utility for I2C communication on Raspberry Pi using Igpio library	62
ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/uPWM.h	
Includes source code for Hardware PWM generation on Raspberry Pi 4	67
ROS2/ros2_scara_ws/src/joint_communication/src/joint_comm_node.cpp	70
ROS2/ros2_scara_ws/src/joint_communication/src/mGripper.cpp	71
ROS2/ros2_scara_ws/src/joint_communication/src/mJoint.cpp	72
ROS2/ros2_scara_ws/src/joint_communication/src/mJointCom.cpp	72
ROS2/ros2 scara ws/src/joint communication/src/ul2C.cpp	73

8 File Index

Chapter 5


Class Documentation

5.1 Gripper Class Reference

Gripper object to interact with the robot gripper.

#include <mGripper.h>

Collaboration diagram for Gripper:



Public Member Functions

- Gripper (void)
- int init (void)

Placeholder, does nothing.

• int deinit (void)

Placeholder, does nothing.

• int enable (void)

Prepares the servo for use.

• int disable (void)

Disables the servo.

• int setPosition (float width)

Sets the gripper width in mm from the closed position.

Private Attributes

RPI_PWM pwm

5.1.1 Detailed Description

Gripper object to interact with the robot gripper.

The gripper must be a PWM controlled servo.

5.1.2 Constructor & Destructor Documentation

5.1.2.1 Gripper()

```
Gripper::Gripper (
     void )
```

5.1.3 Member Function Documentation

5.1.3.1 deinit()

Placeholder, does nothing.

Returns

0

5.1.3.2 disable()

Disables the servo.

Stops the servo and disables the PWM generation.

Returns

non-zero error code.

5.1.3.3 enable()

Prepares the servo for use.

Starts the PWM generation but does not set a position. Must be called before a position is set. The PWM pin is GPIO18. PWM chip is 0, channel 0. *

Returns

non-zero error code.

5.1.3.4 init()

```
int Gripper::init (
     void )
```

Placeholder, does nothing.

Returns

0

5.1.3.5 setPosition()

Sets the gripper width in mm from the closed position.

Arguments outside the allowed range are bounded to limit.

Parameters

width | width in mm. 30 - 85 mm are currently allowed. With a new gripper this should be changed.

5.1.4 Member Data Documentation

5.1.4.1 pwm

```
RPI_PWM Gripper::pwm [private]
```

The documentation for this class was generated from the following files:

- ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mGripper.h
- ROS2/ros2_scara_ws/src/joint_communication/src/mGripper.cpp

5.2 Joint Class Reference

Representing a single joint on the I2C bus.

```
#include <mJoint.h>
```

Public Member Functions

- Joint (const int address, const std::string name, const float gearRatio, const int offset)
- int init (void)
- · int deinit (void)
- int printInfo (void)
- int getPosition (float &angle)
- · int setPosition (float angle)
- int getVelocity (float °ps)
- int setVelocity (float degps)
- int checkOrientation (float angle=10.0)
- int enable (u int8 t driveCurrent, u int8 t holdCurrent)

Initialize the joint and engages motor.

int disable (void)

disenganges the joint motor without closing i2c handle

int home (u_int8_t direction, u_int8_t rpm, int8_t sensitivity, u_int8_t current)

Homes the motor.

int stop (bool mode)

Stops the motor.

• int disableCL (void)

Disables the Closed-Loop PID Controller.

• int setDriveCurrent (u_int8_t current)

Set the Drive Current.

• int setHoldCurrent (u_int8_t current)

Set the Hold Current.

• int setBrakeMode (u_int8_t mode)

Set Brake Mode.

int getStall (u_int8_t &stall)

checks if the motor is stalled

• int enableStallguard (u_int8_t sensitivity)

Enable encoder stall detection. A detected stall can be reset by homeing.

int getIsHomed (u_int8_t &homed)

retrieves the status flags from the joint and checks if the joint is homed.

• int getIsHomed (void)

retrieves the status flags from the joint.

bool isHomed (void)

Get the isHomed state variable saved locally.

int getIsSetup (u_int8_t &setup)

checks if the joint is setup from the joint

int getIsSetup (void)

checks if the joint is setup from the joint

- bool isSetup (void)
- int moveSteps (int32_t steps)
- int checkCom (void)
- u_int8_t getFlags (void)

5.2 Joint Class Reference 13

Public Attributes

· std::string name

Private Types

```
    enum stp_reg_t {
        PING = 0x0f , SETUP = 0x10 , SETRPM = 0x11 , GETDRIVERRPM = 0x12 ,
        MOVESTEPS = 0x13 , MOVEANGLE = 0x14 , MOVETOANGLE = 0x15 , GETMOTORSTATE = 0x16 ,
        RUNCOTINOUS = 0x17 , ANGLEMOVED = 0x18 , SETCURRENT = 0x19 , SETHOLDCURRENT = 0x1A ,
        SETMAXACCELERATION = 0x1B , SETMAXDECELERATION = 0x1C , SETMAXVELOCITY = 0x1D ,
        ENABLESTALLGUARD = 0x1E ,
        DISABLESTALLGUARD = 0x1F , CLEARSTALL = 0x20 , ISSTALLED = 0x21 , SETBRAKEMODE = 0x22 ,
        ENABLEPID = 0x23 , DISABLEPID = 0x24 , ENABLECLOSEDLOOP = 0x25 , DISABLECLOSEDLOOP =
        0x26 ,
        SETCONTROLTHRESHOLD = 0x27 , MOVETOEND = 0x28 , STOP = 0x29 , GETPIDERROR = 0x2A ,
        CHECKORIENTATION = 0x2B , GETENCODERRPM = 0x2C , HOME = 0x2D , ISHOMED = 0x2E ,
        ISSETUP = 0x2F }
```

register and command definitions

Private Member Functions

```
    template<typename T >
        int read (const stp_reg_t reg, T &data, u_int8_t &flags)
        Wrapper function to request data from the I2C slave.
    template<typename T >
        int write (const stp_reg_t reg, T data, u_int8_t &flags)
        Wrapper function to send command to the I2C slave.
```

Private Attributes

```
    u_int8_t flags = 0x00
        State flags transmitted with every I2C transaction.
    u_int8_t ishomed = 0
        flag if homed
    u_int8_t issetup = 0
        flag is setup
    int address
        I2C adress.
    float gearRatio = 1
        gear ratio from encoder units to joint units
    int offset = 0
        offset in degrees or mm from encoder zero to joint zero.
    int handle = -1
        I2C bus handle.
```

5.2.1 Detailed Description

Representing a single joint on the I2C bus.

5.2.2 Member Enumeration Documentation

5.2.2.1 stp_reg_t

```
enum Joint::stp_reg_t [private]
```

register and command definitions

a register can be read (R) or written (W), each register has a size in bytes. The payload can be split into multiple values or just be a single value. Note that not all functions are implemented.

Enumerator

PING	R; Size: 1; [(char) ACK].
SETUP	W; Size: 2; [(uint8) holdCurrent, (uint8) driveCurrent].
SETRPM	W; Size: 4; [(float) RPM].
GETDRIVERRPM	
MOVESTEPS	W; Size: 4; [(int32) steps].
MOVEANGLE	
MOVETOANGLE	W; Size: 4; [(float) degrees].
GETMOTORSTATE	
RUNCOTINOUS	
ANGLEMOVED	R; Size: 4; [(float) degrees].
SETCURRENT	W; Size: 1; [(uint8) driveCurrent].
SETHOLDCURRENT	W; Size: 1; [(uint8) holdCurrent].
SETMAXACCELERATION	
SETMAXDECELERATION	
SETMAXVELOCITY	
ENABLESTALLGUARD	W; Size: 1; [(uint8) threshold].
DISABLESTALLGUARD	
CLEARSTALL	
ISSTALLED	R; Size: 1; [(uint8) isStalled].
SETBRAKEMODE	W; Size: 1; [(uint8) mode].
ENABLEPID	
DISABLEPID	
ENABLECLOSEDLOOP	
DISABLECLOSEDLOOP	W; Size: 1; [(uint8) 0].
SETCONTROLTHRESHOLD	
MOVETOEND	
STOP	W; Size: 1; [(uint8) mode].
GETPIDERROR	
CHECKORIENTATION	W; Size: 4; [(float) degrees].
GETENCODERRPM	R; Size: 4; [(float) RPM].
HOME	W; Size: 4; [(uint8) current, (int8) sensitivity, (uint8) speed, (uint8) direction].
ISHOMED	R; Size: 1; [(uint8) isStalled].
ISSETUP	R; Size: 1; [(uint8) isStalled].
	1

5.2 Joint Class Reference 15

5.2.3 Constructor & Destructor Documentation

5.2.3.1 Joint()

5.2.4 Member Function Documentation

5.2.4.1 checkCom()

5.2.4.2 checkOrientation()

5.2.4.3 deinit()

5.2.4.4 disable()

disenganges the joint motor without closing i2c handle

Returns

error code.

5.2.4.5 disableCL()

Disables the Closed-Loop PID Controller.

Returns

error code.

5.2.4.6 enable()

Initialize the joint and engages motor.

Parameters

driveCurrent	drive current in 0-100 % of 2.5A output (check uStepper doc.)
holdCurrent	hold current in 0-100 % of 2.5A output (check uStepper doc.)

Returns

error code.

5.2.4.7 enableStallguard()

```
int Joint::enableStallguard (  u\_int8\_t \ \textit{sensitivity} \ )
```

Enable encoder stall detection. A detected stall can be reset by homeing.

Parameters

sensitivity	Encoder stalldetect sensitivity - From -100 to 10 where lower number is less sensitive and higher is	
	more sensitive	

5.2.4.8 getFlags()

get driver state flags

Returns

flags.

5.2.4.9 getIsHomed() [1/2]

```
int Joint::getIsHomed (  u\_int8\_t \text{ \& homed )}
```

retrieves the status flags from the joint and checks if the joint is homed.

Parameters

homed	not homed: 0, homed: 1
nomea	not nomea. U. nomea. T

Returns

error code.

5.2 Joint Class Reference 17

5.2.4.10 getIsHomed() [2/2]

retrieves the status flags from the joint.

This overload does not return the value of isHomed variable, use Joint::isHomed() instead.

Returns

error code.

5.2.4.11 getIsSetup() [1/2]

checks if the joint is setup from the joint

Parameters

```
setup | not setup: 0, setup: 1
```

Returns

error code.

5.2.4.12 getIsSetup() [2/2]

checks if the joint is setup from the joint

Returns

error code.

5.2.4.13 getPosition()

5.2.4.14 getStall()

checks if the motor is stalled

Parameters

stall not stalled: 0, stalled: 1	
----------------------------------	--

Returns

error code.

5.2.4.15 getVelocity()

5.2.4.16 home()

Homes the motor.

Parameters

direction	CCW: 0, CW: 1.	
rpm	speed of motor in rpm > 10.	
sensitivity	Encoder stalldetect sensitivity - From -100 to 10 where lower number is less sensitive and higher is	
	more sensitive	
current	homeing current, determines how easy it is to stop the motor and thereby provoke a stall	

Returns

error code.

5.2.4.17 init()

```
int Joint::init (
     void )
```

5.2.4.18 isHomed()

Get the isHomed state variable saved locally.

To retrieve the actual state call Joint::getIsHomed()

5.2 Joint Class Reference

Returns

local isHomed state variable.

5.2.4.19 isSetup()

Returns

the isSetup state variable.

5.2.4.20 moveSteps()

5.2.4.21 printlnfo()

5.2.4.22 read()

Wrapper function to request data from the I2C slave.

Allocates a buffer of size sizeof(T) + RFLAGS_SIZE. invokes readFromI2CDev(), and copies the received payload to *data* and the transmisison flags to *flags*. See Joint::flags for details.

Todo

- Implement a return code for read only functions
- · Implement clearStall function

Template Parameters

T	Datatype of value to be transmitted
---	-------------------------------------

Parameters

reg	stp_reg_t register to read
data	reference to store payload.

Parameters

flags reference to a byte which stores the return flags

Returns

0 on OK, negative on error

5.2.4.23 setBrakeMode()

Set Brake Mode.

Parameters

```
mode Freewheel: 0, Coolbrake: 1, Hardbrake: 2
```

Returns

error code.

5.2.4.24 setDriveCurrent()

Set the Drive Current.

Warning

This function is unreliable and not well tested. Use enable() instead!

Parameters

```
current 0% - 100% of driver current
```

Returns

error code.

5.2.4.25 setHoldCurrent()

Set the Hold Current.

5.2 Joint Class Reference 21

Warning

This function is unreliable and not well tested. Use enable() instead!

Parameters

```
current 0% - 100% of driver current
```

Returns

error code.

5.2.4.26 setPosition()

5.2.4.27 setVelocity()

5.2.4.28 stop()

```
int Joint::stop (
    bool mode )
```

Stops the motor.

Note

When stopping the motor in soft mode, wait sufficiently long until the motor has stopped. Since the stop() function in the motor controller is blocking. Continously checking the busy flag also might interfere with the stop() function on the controller side.

Parameters

```
mode Hard: 0, Soft: 1
```

Returns

error code.

5.2.4.29 write()

```
template<typename T >
int Joint::write (
```

```
const stp_reg_t reg,
T data,
u_int8_t & flags ) [private]
```

Wrapper function to send command to the I2C slave.

Allocates a buffer of size sizeof(T) + RFLAGS_SIZE. Copyies *data* to the buffer and invokes writeTol2CDev(). The flags received from the transaction are copied to *flags*. The flags are described in Joint::read().

Template Parameters

T	Datatype of value to be transmitted
---	-------------------------------------

Parameters

reg	stp_reg_t command to execute
data	payload to transmit. It is the users responsibility to populate the right amount of data for the relevant register
flags	reference to a byte which stores the return flags

Returns

0 on OK, negative on error

5.2.5 Member Data Documentation

5.2.5.1 address

```
int Joint::address [private]
```

I2C adress.

5.2.5.2 flags

```
u_int8_t Joint::flags = 0x00 [private]
```

State flags transmitted with every I2C transaction.

The transmission flags purpose are to transmit the joints current state. Note: They can not be used as error indication of the execution of a transmitted write command, since commands are executed after the I2C transaction is completed. The status flags are one byte with following structure:

BIT7	BIT6	BIT5	BIT4	BIT3	BIT2	BIT1	BIT0
reserved	reserved	reserved	reserved	SETUP	HOMED	BUSY	STALL

STALL is set if a stall from the stall detection is sensed and the joint is stopped. The flag is cleared when the joint is homed.

BUSY is set if the slave is busy processing a previous command.

5.2 Joint Class Reference 23

HOMED is set if the joint is homed. Movement is only allowed if this flag is clear **SETUP** is set if the joint is setup after calling Joint::enable()

5.2.5.3 gearRatio

```
float Joint::gearRatio = 1 [private]
```

gear ratio from encoder units to joint units

5.2.5.4 handle

```
int Joint::handle = -1 [private]
```

I2C bus handle.

5.2.5.5 ishomed

```
u_int8_t Joint::ishomed = 0 [private]
```

flag if homed

5.2.5.6 issetup

```
u_int8_t Joint::issetup = 0 [private]
```

flag is setup

5.2.5.7 name

std::string Joint::name

5.2.5.8 offset

```
int Joint::offset = 0 [private]
```

offset in degrees or mm from encoder zero to joint zero.

The documentation for this class was generated from the following files:

- ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.h
- ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.hpp
- ROS2/ros2_scara_ws/src/joint_communication/src/mJoint.cpp

5.3 Joint comms Class Reference

Communication object for all joints.

```
#include <mJointCom.h>
```

Public Member Functions

- · Joint comms (void)
- ~Joint_comms ()
- int init (void)

Initializes all joints.

· int deinit (void)

Frees all joints from the I2C bus.

void addJoint (const int address, const std::string name, const float gearRatio, const int offset)

int enables (std::vector< u_int8_t > driveCurrent_v, std::vector< u_int8_t > holdCurrent_v)
 Engages the joints.

• int enables (u_int8_t driveCurrent, u_int8_t holdCurrent)

Engages the joints with the same current settings for all joints.

· int disables (void)

Disenganges the joint without closing i2c handle.

• int home (std::string name, u_int8_t direction, u_int8_t rpm, int8_t sensitivity, u_int8_t current)

Executes the homing sequence of a joint.

int getPositions (std::vector< float > &angle_v)

Get the positions of all joints.

int setPositions (std::vector< float > angle_v)

Set the positions of all joints.

int getVelocities (std::vector< float > °ps_v)

Get the velocities of all joints.

int setVelocities (std::vector< float > degps_v)

Set the velocities of all joints.

int checkOrientations (std::vector< float > angle v)

Sequentially checks the orientations of each joint.

int checkOrientations (float angle=10.0)

Overload to use standard angle of 10 degrees.

• int stops (bool mode)

Stops the motors.

int disableCLs (void)

Disables the Closed-Loop PID Controllers.

int setDriveCurrents (std::vector< u_int8_t > current)

Set the drive Currents.

• int setDriveCurrents (u_int8_t current)

Overload to set all drive currents to the same value.

int setHoldCurrents (std::vector< u_int8_t > current)

Set the Hold Currents.

int setHoldCurrents (u_int8_t current)

Overload to set all hold currents to the same value.

int setBrakeModes (u_int8_t mode)

Set Brake Modes.

int enableStallguards (std::vector< u_int8_t > thresholds)

Enable encoder stall detection.

Public Attributes

std::vector < Joint > joints
 Internal vector storing the Joint objects.

5.3.1 Detailed Description

Communication object for all joints.

CLass handling interfacing with the joints.

5.3.2 Constructor & Destructor Documentation

5.3.2.1 Joint_comms()

5.3.2.2 \sim Joint_comms()

```
Joint_comms::~Joint_comms ( )
```

5.3.3 Member Function Documentation

5.3.3.1 addJoint()

add Joints.

Appends a joint to internal vector.

Parameters

addresses	1-byte I2C device adress (0x11 0x14) for J1 J4
names	string device name for output logs
gearRatio	gear ratio of joint. This is used to transform position and velocity commands in joint units to the stepper units. Signed: sign depends if homed CW or CCW. J1: 35; J2: -360/4 (4 mm per revolution); J3: 24; J4: 12;
offset	offset between encoder zero and joint zero (in joint units). J1: TBD; J2: -TBD (negative because homed at top); J3: TBD; J4: TBD;

Todo

- · Measure joint ranges
- · Investigate if possible to make independent of homing

5.3.3.2 checkOrientations() [1/2]

Overload to use standard angle of 10 degrees.

Returns

error code.

5.3.3.3 checkOrientations() [2/2]

Sequentially checks the orientations of each joint.

This function must only be called after the joint has been powered down. This function must be called after the joint has been enabled with enables() and before any movement.

Parameters

an	gle↩	vector of degrees to rotate to check the orientation. Should be small values of a few degrees.
_ <i>v</i>		

Returns

error code.

Todo

- · Only execute if not performed before
- save in private flag and inhibit movement if this has not been executed.

5.3.3.4 deinit()

Frees all joints from the I2C bus.

Deinitializes all joints by removing them from the I2C bus.

Returns

0 on success, non-zero otherwise

5.3.3.5 disableCLs()

Disables the Closed-Loop PID Controllers.

Returns

error code.

5.3.3.6 disables()

Disenganges the joint without closing i2c handle.

Call this function when the joint should be in freedrive mode.

Returns

error code.

5.3.3.7 enables() [1/2]

Engages the joints.

Sets the drive and hold currents for each joint and engages the motor. Currents are in percent of driver max. output (2.5A, check with datasheet)

Parameters

driveCurrent←	vector of drive currents 0-100. the i'th vector entry sets the current for the i'th added joint.
_v	
holdCurrent⇔	vector of hold currents 0-100. the i'th vector entry sets the current for the i'th added joint.
_ <i>v</i>	

Returns

error code.

5.3.3.8 enables() [2/2]

```
int Joint_comms::enables (
```

```
u_int8_t driveCurrent,
u_int8_t holdCurrent )
```

Engages the joints with the same current settings for all joints.

In this overload the same drive and hold currents are written to every joint.

Parameters

driveCurrent	drive current 0-100.
holdCurrent	hold current 0-100.

Returns

error code.

5.3.3.9 enableStallguards()

Enable encoder stall detection.

If the PID error exceeds the set threshold a stall is triggered and the motor disabled. A detected stall can be reset by homeing.

Parameters

```
thresholds Vector of thresholds. 0 - 255 where lower is more sensitive.
```

5.3.3.10 getPositions()

Get the positions of all joints.

The current positions of all joints are returned. The units are degrees and mm for revolute and prismatic joints respectively.

Parameters

angle↩	Reference to allocated vector of appropriate size to hold all joint positions.
_ <i>v</i>	

Returns

error code.

5.3.3.11 getVelocities()

```
int Joint_comms::getVelocities ( std::vector < \ float \ > \ \& \ degps\_v \ )
```

Get the velocities of all joints.

The current velocities of all joints are returned. The units are degrees/s and mm/s for revolute and prismatic joints respectively.

Parameters

degps⇔	Reference to allocated vector of appropriate size to hold all joint velocities.
_ <i>V</i>	

Returns

error code.

5.3.3.12 home()

```
int Joint_comms::home (
    std::string name,
    u_int8_t direction,
    u_int8_t rpm,
    int8_t sensitivity,
    u_int8_t current)
```

Executes the homing sequence of a joint.

The joint will drive in the specified direction with the specified speed until a resistance which drives the current above the specified threshold is encountered. At this point the stepper stops and zeros the encoder.

Parameters

name	joint name.
direction	CCW: 0, CW: 1.
rpm	speed of motor in rpm > 10
sensitivity	Encoder stalldetect sensitivity - From -100 to 10 where lower number is less sensitive and higher is more sensitive
current	homeing current, determines how easy it is to stop the motor and thereby provoke a stall

Returns

error code.

5.3.3.13 init()

Initializes all joints.

30 Class Documentation

Warning

Add some joints using addJoint() before calling this function. Iterates over all joints and initializes them on the I2C bus and tests if they are responsive.

Returns

0 on success, non-zero otherwise

5.3.3.14 setBrakeModes()

Set Brake Modes.

Applies the same brake modes to all joints. usefull to disengage all motors.

Parameters

```
mode Freewheel: 0, Coolbrake: 1, Hardbrake: 2
```

Returns

error code.

5.3.3.15 setDriveCurrents() [1/2]

Set the drive Currents.

Warning

This function is unreliable and not well tested. Use enables() instead!

Parameters

```
current 0% - 100% of driver current
```

Returns

error code.

5.3.3.16 setDriveCurrents() [2/2]

Overload to set all drive currents to the same value.

Warning

This function is unreliable and not well tested. Use enables() instead!

Parameters

```
current 0% - 100% of driver current
```

Returns

error code.

5.3.3.17 setHoldCurrents() [1/2]

```
int Joint_comms::setHoldCurrents ( std::vector < \ u\_int8\_t \ > \ current \ )
```

Set the Hold Currents.

Warning

This function is unreliable and not well tested. Use enables() instead!

Parameters

current	0% - 100% of driver current

Returns

error code.

5.3.3.18 setHoldCurrents() [2/2]

Overload to set all hold currents to the same value.

Warning

This function is unreliable and not well tested. Use enables() instead!

Parameters

current	0% - 100% of driver current
---------	-----------------------------

32 Class Documentation

Returns

error code.

5.3.3.19 setPositions()

```
int Joint_comms::setPositions ( std::vector < \ float \ > \ angle\_v \ )
```

Set the positions of all joints.

Set new target positons of all joints. The units are degrees and mm for revolute and prismatic joints respectively.

Parameters

angle⊷	Vector of new target positions.
_ <i>v</i>	

Returns

error code.

5.3.3.20 setVelocities()

```
int Joint_comms::setVelocities ( std::vector < \ float \ > \ degps\_v \ )
```

Set the velocities of all joints.

Set new target positons of all joints. The units are degrees and mm for revolute and prismatic joints respectively.

Parameters

degps⇔	Vector of new target velocities.
_v	

Returns

error code.

5.3.3.21 stops()

Stops the motors.

Stops all motors either soft or hard.

Parameters

mode	Hard: 0, Soft: 1
------	------------------

Returns

error code.

5.3.4 Member Data Documentation

5.3.4.1 joints

```
std::vector<Joint> Joint_comms::joints
```

Internal vector storing the Joint objects.

A Joint can be added by invoking addJoint()

The documentation for this class was generated from the following files:

- ROS2/ros2 scara ws/src/joint communication/include/joint communication/mJointCom.h
- ROS2/ros2_scara_ws/src/joint_communication/src/mJointCom.cpp

5.4 RPI PWM Class Reference

PWM class for the Raspberry PI 4 and 5.

```
#include <uPWM.h>
```

Public Member Functions

- int start (int channel, int frequency, float duty_cycle=0, int chip=2)
- void stop ()
- ∼RPI PWM ()
- int setDutyCycle (float v) const

Private Member Functions

- · void setPeriod (int ns) const
- int setDutyCycleNS (int ns) const
- void enable () const
- · void disable () const
- int writeSYS (std::string filename, int value) const

Private Attributes

- int per = 0
- std::string chippath
- std::string pwmpath

34 Class Documentation

5.4.1 Detailed Description

PWM class for the Raspberry PI 4 and 5.

5.4.2 Constructor & Destructor Documentation

```
5.4.2.1 ∼RPI_PWM()
```

```
RPI_PWM::~RPI_PWM ( ) [inline]
```

5.4.3 Member Function Documentation

5.4.3.1 disable()

```
void RPI_PWM::disable ( ) const [inline], [private]
```

5.4.3.2 enable()

```
void RPI_PWM::enable ( ) const [inline], [private]
```

5.4.3.3 setDutyCycle()

Sets the duty cycle.

Parameters

V	The duty cycle in percent.
return	>0 on success and -1 after an error.

5.4.3.4 setDutyCycleNS()

```
int RPI_PWM::setDutyCycleNS (
                int ns ) const [inline], [private]
```

5.4.3.5 setPeriod()

```
void RPI_PWM::setPeriod (
          int ns ) const [inline], [private]
```

5.4.3.6 start()

```
int RPI_PWM::start (
    int channel,
    int frequency,
    float duty_cycle = 0,
    int chip = 2 ) [inline]
```

Starts the PWM

Parameters

channel	The GPIO channel which is 2 or 3 for the RPI5
frequency	The PWM frequency
duty_cycle	The initial duty cycle of the PWM (default 0)
chip	The chip number (for RPI5 it's 2)
return	>0 on success and -1 if an error has happened.

5.4.3.7 stop()

```
void RPI_PWM::stop ( ) [inline]
```

Stops the PWM

5.4.3.8 writeSYS()

5.4.4 Member Data Documentation

5.4.4.1 chippath

```
std::string RPI_PWM::chippath [private]
```

5.4.4.2 per

```
int RPI_PWM::per = 0 [private]
```

5.4.4.3 pwmpath

```
std::string RPI_PWM::pwmpath [private]
```

The documentation for this class was generated from the following file:

• ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/uPWM.h

36 Class Documentation


Chapter 6

File Documentation

6.1 Arduino/joint/configuration.h File Reference

Configuration definitions for Joint 1 to Joint 4.

This graph shows which files directly or indirectly include this file:



Macros

• #define ADR 0x11

I2C adress of joint n is 0x1n.

• #define MAXACCEL 10000

Maximum acceleration in steps/ s^{\wedge} 2. Can be set for each joint depending on inertia. If set to high stalls might trigger since PID error grows too large.

• #define MAXVEL 800

Maximum velocity in steps/s. Can be set for each joint. If set to high stalls might trigger since PID error grows too large.

6.1.1 Detailed Description

Configuration definitions for Joint 1 to Joint 4.

Author

Sebastian Storz

Version

0.1

Date

2025-05-27

Copyright

Copyright (c) 2025

This file shall be included AFTER one of J1, J2, J3 or J4 have been defined.

6.1.2 Macro Definition Documentation

6.1.2.1 ADR

#define ADR 0x11

I2C adress of joint n is 0x1n.

6.1.2.2 MAXACCEL

#define MAXACCEL 10000

Maximum acceleration in steps/s $^{\wedge}$ 2. Can be set for each joint depending on inertia. If set to high stalls might trigger since PID error grows too large.

6.1.2.3 MAXVEL

#define MAXVEL 800

Maximum velocity in steps/s. Can be set for each joint. If set to high stalls might trigger since PID error grows too large.

6.2 configuration.h 39

6.2 configuration.h


Go to the documentation of this file.

```
00001
00014 #ifndef CONFIGURATION_H
00015 #define CONFIGURATION_H
00016
00017 #if defined(J1)
00019 #define ADR 0x11
00020 #define MAXACCEL 10000
00021 #define MAXVEL 800
00022
00023 #elif defined(J2)
00024 #define ADR 0x12
00025 #define MAXACCEL 10000
00026 #define MAXVEL 800
00027
00028 #elif defined(J3)
00029 #define ADR 0x13
00030 #define MAXACCEL 10000
00031 #define MAXVEL 800
00032
00033 #elif defined(J4)
00033 #effi define (04)
00034 #define ADR 0x14
00035 #define MAXACCEL 10000
00036 #define MAXVEL 800
00037 #else
00038
00039 /\star Below only defined for documentation \star/
00043 #define ADR 0x11
00044
00049 #define MAXACCEL 10000
00055 #define MAXVEL 800 00056 #error "No Joint has been defined. Define one of 'JX' where X 1,2,3,4" 00057 #endif
00058
00059 #endif
```


6.3 Arduino/joint/joint.h File Reference

joint firmware header

#include <Arduino.h>
Include dependency graph for joint.h:



This graph shows which files directly or indirectly include this file:



Macros

- #define ACK 'O'
- · #define NACK 'N'
- #define MAX BUFFER 4

Maximum size of I2C Payload in bytes.

• #define RFLAGS_SIZE 1

Size of the return flags in bytes.

• #define DUMP BUFFER(buffer, size)

Macro to dump a buffer to the serial console.

Enumerations

```
    enum stp_reg_t {
        PING = 0x0f , SETUP = 0x10 , SETRPM = 0x11 , GETDRIVERRPM = 0x12 ,
        MOVESTEPS = 0x13 , MOVEANGLE = 0x14 , MOVETOANGLE = 0x15 , GETMOTORSTATE = 0x16 ,
        RUNCOTINOUS = 0x17 , ANGLEMOVED = 0x18 , SETCURRENT = 0x19 , SETHOLDCURRENT = 0x1A ,
        SETMAXACCELERATION = 0x1B , SETMAXDECELERATION = 0x1C , SETMAXVELOCITY = 0x1D ,
        ENABLESTALLGUARD = 0x1E ,
        DISABLESTALLGUARD = 0x1F , CLEARSTALL = 0x20 , ISSTALLED = 0x21 , SETBRAKEMODE = 0x22 ,
        ENABLEPID = 0x23 , DISABLEPID = 0x24 , ENABLECLOSEDLOOP = 0x25 , DISABLECLOSEDLOOP =
        0x26 ,
        SETCONTROLTHRESHOLD = 0x27 , MOVETOEND = 0x28 , STOP = 0x29 , GETPIDERROR = 0x2A ,
        CHECKORIENTATION = 0x2B , GETENCODERRPM = 0x2C , HOME = 0x2D , ISHOMED = 0x2E ,
        ISSETUP = 0x2F }
```

Functions

```
    template < typename T > void readValue (T &val, uint8_t *rxBuf, size_t rx_length)
        Reads a value from a buffer to a value of the specified type.
    template < typename T > int writeValue (const T val, uint8_t *txBuf, size_t &tx_length)
```

Writes a value of the specified type to a buffer.

register and command definitions

6.3.1 Detailed Description

joint firmware header

Author

Sebastian Storz

Version

0.1

Date

2025-05-27

Copyright

Copyright (c) 2025

This file contains definitions and macros for the joint firmware.

6.3.2 Macro Definition Documentation

6.3.2.1 ACK

```
#define ACK 'O'
```

6.3.2.2 DUMP_BUFFER

Value:

```
{
    Serial.print("Buffer dump: ");
    for (size_t i = 0; i < size; i++) \
    {
        Serial.print(buffer[i], HEX);
        Serial.print(" ");
    }
    Serial.println();
}</pre>
```

Macro to dump a buffer to the serial console.

Parameters

	buffer	pointer to a buffer to dump to the console
ŀ		number of bytes to dump

6.3.2.3 MAX_BUFFER

```
#define MAX_BUFFER 4
```

Maximum size of I2C Payload in bytes.

4 bytes used to transmit floats and int32_t

6.3.2.4 NACK

#define NACK 'N'

6.3.2.5 RFLAGS_SIZE

```
#define RFLAGS_SIZE 1
```

Size of the return flags in bytes.

Only one byte used and hence set to 1.

6.3.3 Enumeration Type Documentation

6.3.3.1 stp_reg_t

```
enum stp_reg_t
```

register and command definitions

a register can be read (R) or written (W), each register has a size in bytes. The payload can be split into multiple values or just be a single value. Note that not all functions are implemented.

Enumerator

PING	R; Size: 1; [(char) ACK].
SETUP	W; Size: 2; [(uint8) holdCurrent, (uint8) driveCurrent].
SETRPM	W; Size: 4; [(float) RPM].
GETDRIVERRPM	
MOVESTEPS	W; Size: 4; [(int32) steps].
MOVEANGLE	
MOVETOANGLE	W; Size: 4; [(float) degrees].
GETMOTORSTATE	
RUNCOTINOUS	
ANGLEMOVED	R; Size: 4; [(float) degrees].
SETCURRENT	W; Size: 1; [(uint8) driveCurrent].
SETHOLDCURRENT	W; Size: 1; [(uint8) holdCurrent].
SETMAXACCELERATION	
SETMAXDECELERATION	
SETMAXVELOCITY	
ENABLESTALLGUARD	W; Size: 1; [(uint8) threshold].

Enumerator

DISABLESTALLGUARD	
CLEARSTALL	
ISSTALLED	R; Size: 1; [(uint8) isStalled].
SETBRAKEMODE	W; Size: 1; [(uint8) mode].
ENABLEPID	
DISABLEPID	
ENABLECLOSEDLOOP	
DISABLECLOSEDLOOP	W; Size: 1; [(uint8) 0].
SETCONTROLTHRESHOLD	
MOVETOEND	
STOP	W; Size: 1; [(uint8) mode].
GETPIDERROR	
CHECKORIENTATION	W; Size: 4; [(float) degrees].
GETENCODERRPM	R; Size: 4; [(float) RPM].
HOME	W; Size: 4; [(uint8) current, (int8) sensitivity, (uint8) speed, (uint8) direction].
ISHOMED	R; Size: 1; [(uint8) isStalled].
ISSETUP	R; Size: 1; [(uint8) isStalled].

6.3.4 Function Documentation

6.3.4.1 readValue()

Reads a value from a buffer to a value of the specified type.

Parameters

val	Reference to output variable
rxBuf	Buffer to read value from
rx_length	Length of the buffer

6.3.4.2 writeValue()

Writes a value of the specified type to a buffer.

Parameters

val	Reference to input variable
txBuf	pointer to tx buffer
tx_length	Length of the buffer returne

Returns

0 On success

joint.h 6.4

Go to the documentation of this file.


```
00001
00014 #ifndef JOINT_H
00015 #define JOINT H
00016 #include <Arduino.h>
00018 #define ACK 'O'
00019 #define NACK 'N'
00020
00026 #define MAX_BUFFER 4 // Bytes
00027
00033 #define RFLAGS_SIZE 1
00034
00041 #define DUMP_BUFFER(buffer, size)
00042
           Serial.print("Buffer dump: ");
00043
00044
           for (size_t i = 0; i < size; i++)
00045
00046
              Serial.print(buffer[i], HEX);
00047
              Serial.print(" ");
00048
00049
           Serial.println();
00050
         }
00051
00060 enum stp_reg_t
00061 {
         PING = 0x0f,
SETUP = 0x10,
SETRPM = 0x11,
00062
00063
00064
00065
         GETDRIVERRPM = 0x12,
         MOVESTEPS = 0x13,
MOVEANGLE = 0x14,
00066
00067
00068
         MOVETOANGLE = 0x15,
00069
         GETMOTORSTATE = 0x16
00070
         RUNCOTINOUS = 0x17.
         ANGLEMOVED = 0x18,
SETCURRENT = 0x19,
00071
00072
00073
         SETHOLDCURRENT = 0x1A,
         SETMAXACCELERATION = 0x1B,
SETMAXDECELERATION = 0x1C,
SETMAXVELOCITY = 0x1D,
00074
00075
00076
00077
         ENABLESTALLGUARD = 0x1E,
00078
         DISABLESTALLGUARD = 0x1F,
00079
         CLEARSTALL = 0x20,
         ISSTALLED = 0x21,
08000
00081
         SETBRAKEMODE = 0x22,
         ENABLEPID = 0x23,
DISABLEPID = 0x24,
00082
00083
         ENABLECLOSEDLOOP = 0x25,
DISABLECLOSEDLOOP = 0x26,
00084
00085
00086
         SETCONTROLTHRESHOLD = 0x27,
00087
         MOVETOEND = 0x28,
         STOP = 0x29,
00088
         GETPIDERROR = 0x2A,
CHECKORIENTATION = 0x2B,
00089
00090
00091
         GETENCODERRPM = 0x2C,
00092
         HOME = 0x2D,
        ISHOMED = 0x2E,
ISSETUP = 0x2F
00093
00094
00095 };
00096
00103 template <typename T>
00104 void readValue(T &val, uint8_t *rxBuf, size_t rx_length)
```

```
00105 {
00106    memcpy(&val, rxBuf, rx_length);
00107 }
00108
00116 template <typename T>
00117 int writeValue(const T val, uint8_t *txBuf, size_t &tx_length)
00118 {
00119    tx_length = sizeof(T);
00120    memcpy(txBuf, &val, tx_length);
00121    return 0;
00122 }
00123
00124 #endif
```

6.5 Arduino/joint/joint.ino File Reference

joint firmware

```
#include <UstepperS32.h>
#include <Wire.h>
#include "joint.h"
#include "configuration.h"
Include dependency graph for joint.ino:
```



Macros

• #define J4

Define either joint that is to be flashed.

Functions

void stepper receive handler (uint8 t reg)

Handles commands received via I2C.

void stepper_request_handler (uint8_t reg)

Handles read request received via I2C.

• void receiveEvent (int n)

I2C receive event Handler.

void requestEvent ()

I2C request event Handler.

void setup (void)

Setup Peripherals.

void loop (void)

Main loop.

Variables

```
UstepperS32 stepper
uint8_t reg = 0
uint8_t rx_buf [MAX_BUFFER] = { 0 }
uint8_t tx_buf [MAX_BUFFER+RFLAGS_SIZE] = { 0 }
bool tx_data_ready = 0
bool rx_data_ready = 0
size_t tx_length = 0
size_t rx_length = 0
```

6.5.1 Detailed Description

```
joint firmware

Author
Sebastian Storz

Version
0.1
```

Date

2025-05-27

Copyright

Copyright (c) 2025

This file contains the joint firmware.

6.5.2 Macro Definition Documentation

6.5.2.1 J4

#define J4

Define either joint that is to be flashed.

Define either J1, J2, J3 or J4 and subsequently include configuration.h

6.5.3 Function Documentation

6.5.3.1 loop()

```
void loop (
```

Main loop.

Executes the following:

- 1) if isStallguardEnabled: compares stepper.getPidError() with stallguardThreshold and sets BIT0 of the state byte.
- 2) sets/clears BIT2 of the state byte if the joint is homed or not.
- 3) sets/clears BIT3 of the state byte if the joint is setup or not.
- 4) if rx_data_ready: set BIT1 of the state byte to indicate device is busy. Invoke stepper_receive_handler. Clear BIT1 of the state byte to indicate device is no longer busy

Todo

 why are BIT2 and BIT3 constantly checked and set? Would it be sufficient to do this only invoking the actual functions?

6.5.3.2 receiveEvent()

```
void receiveEvent ( \inf \ n \ )
```

I2C receive event Handler.

Reads the content of the received message. Saves the reg so it can be used in the main loop. If the master invokes the read() function the message contains only the register byte and no payload. If the master invokes the write() the message has a payload of appropriate size for the command. For a read the message looks like this:

- < [REG]
- > [TXBUFn]...[TXBUF2][TXBUF1][TXBUF0]

For a write the message looks like this:

- < [REG][RXBUFn]...[RXBUF2][RXBUF1][RXBUF0]
- > [TXBUFn]...[TXBUF2][TXBUF1][TXBUF0][FLAGS]

The payload is read into the rx_buf, rx_length is set to the payload length and the rx_data_ready flag is set.

Parameters

n the number of bytes read from the controller device

6.5.3.3 requestEvent()

```
void requestEvent ( )
```

I2C request event Handler.

Sends the response data to the master. Every transaction begins with a receive event. This function is only called when the master calls the read() function. Hence this function is only invoked after the receiveEvent() handler has been called. The function calls the stepper_request_handler() which is non-blocking. stepper_request_handler() populates the tx_buf, the current state flags are appended to the tx_buf and then it is send to the master.

6.5.3.4 setup()

```
void setup (
     void )
```

Setup Peripherals.

Setup I2C with the address ADR, and begin Serial for debugging with baudrate 9600.

6.5.3.5 stepper_receive_handler()

Handles commands received via I2C.

Warning

This is a blocking function which may take some time to execute. This function must not be called from an ISR or callback! Call from main loop instead.

All the registers that are inside this handler are considered command which require an action.

Parameters

reg command that should be executed.

6.5.3.6 stepper_request_handler()

Handles read request received via I2C.

Can be invoked from the I2C ISR since reads from the stepper are non-blocking. Also Handling reads and the subsequent wire.write(), did not work from the main loop.

All registers inside this function are regarded as read only.

Parameters

reg register to read.

6.5.4 Variable Documentation

6.5.4.1 reg

```
uint8\_t reg = 0
```

6.5.4.2 rx_buf

```
uint8_t rx_buf[MAX_BUFFER] = { 0 }
```

6.5.4.3 rx_data_ready

```
bool rx_data_ready = 0
```

6.5.4.4 rx_length

```
size_t rx_length = 0
```

6.5.4.5 stepper

UstepperS32 stepper

6.5.4.6 tx_buf

```
uint8_t tx_buf[MAX_BUFFER+RFLAGS_SIZE] = { 0 }
```

6.5.4.7 tx_data_ready

```
bool tx_data_ready = 0
```

6.5.4.8 tx_length


```
size_t tx_length = 0
```

6.6 docs/DOCS_README.md File Reference

6.7 ROS2/ros2_scara_ws/src/joint_communication/include/joint_← communication/common.h File Reference

A file containing utility macros and functions.

This graph shows which files directly or indirectly include this file:



Macros

• #define DUMP_BUFFER(buffer, size)

Macro to dump a buffer to cout.

6.7.1 Detailed Description

A file containing utility macros and functions.

Author

Sebastian Storz

Version

0.1

Date

2025-05-27

Copyright

Copyright (c) 2025

6.8 common.h 51

6.7.2 Macro Definition Documentation

6.7.2.1 DUMP_BUFFER

Macro to dump a buffer to cout.

Parameters

buffer	pointer to a buffer to dump to the console
size	number of bytes to dump

6.8 common.h


Go to the documentation of this file.

```
00011 #ifndef COMMON_H
00012 #define COMMON_H
00013
00014
00021 #define DUMP_BUFFER(buffer, size)
         std::cout « "Buffer dump: ";
00024
         for (size_t i = 0; i < size; i++)
00025
           printf("%#x ", buffer[i]);
00026
00027
00028
         std::cout « std::endl;
00030
00031 #endif // COMMON_H
```


6.9 ROS2/ros2_scara_ws/src/joint_communication/include/joint_← communication/mGripper.h File Reference

File containing the Gripper class.

#include "joint_communication/uPWM.h"
Include dependency graph for mGripper.h:



This graph shows which files directly or indirectly include this file:



Classes

class Gripper
 Gripper object to interact with the robot gripper.

6.9.1 Detailed Description

File containing the Gripper class.

Author

Sebastian Storz

6.10 mGripper.h 53

Version

0.1

Date

2025-05-27

Copyright

Copyright (c) 2025

Include this file for API functions to interact with the gripper.

6.10 mGripper.h


Go to the documentation of this file.

```
00001
00013 #ifndef MGRIPPER_H
00014 #define MGRIPPER_H
00015 #include "joint_communication/uPWM.h"
00016
00023 class Gripper
00024 {
00025 public:
        Gripper(void);
00027
00033
         int init(void);
00034
00040
         int deinit (void);
00041
00050
         int enable(void);
00051
00059
         int disable(void);
00060
         int setPosition(float width);
00067
00068
00069 private:
00070
        RPI_PWM pwm;
00071 };
00072 #endif // MGRIPPER_H
```


6.11 ROS2/ros2_scara_ws/src/joint_communication/include/joint_← communication/mJoint.h File Reference

File including the Joint class.

#include "joint_communication/mJoint.hpp"
Include dependency graph for mJoint.h:



This graph shows which files directly or indirectly include this file:



Classes

class Joint

Representing a single joint on the I2C bus.

Macros

- #define JOINT2ENCODERANGLE(jointAngle, gearRatio, offset) (gearRatio * (jointAngle + offset))
- #define ENCODER2JOINTANGLE(encoderAngle, gearRatio, offset) (encoderAngle / gearRatio offset)

6.12 mJoint.h 55

6.11.1 Detailed Description

File including the Joint class.

Author

Sebastian Storz

Version

0.1

Date

2025-05-29

Copyright

Copyright (c) 2025

6.11.2 Macro Definition Documentation

6.11.2.1 ENCODER2JOINTANGLE

6.11.2.2 JOINT2ENCODERANGLE

6.12 mJoint.h

Go to the documentation of this file.

```
00001 #ifndef MJOINT_H
00013 #define MJOINT_H
00014
00015 #define JOINT2ENCODERANGLE(jointAngle, gearRatio, offset) (gearRatio * (jointAngle + offset))
00016 #define ENCODER2JOINTANGLE(encoderAngle, gearRatio, offset) (encoderAngle / gearRatio - offset)
00017
00022 class Joint
00023 {
00024 public:
00025     Joint(const int address, const std::string name, const float gearRatio, const int offset);
00026     // ~Joint();
00027
00028     int init(void);
00029     int deinit(void);
```


```
int printInfo(void);
00031
        int getPosition(float &angle);
00032
        int setPosition(float angle);
00033
        int getVelocity(float &degps);
00034
        int setVelocity(float degps);
00035
        int checkOrientation(float angle = 10.0);
00036
00043
        int enable(u_int8_t driveCurrent, u_int8_t holdCurrent);
00044
00049
        int disable (void);
00050
00060
        int home(u_int8_t direction, u_int8_t rpm, int8_t sensitivity, u_int8_t current);
00061
        int stop(bool mode);
00070
00075
        int disableCL(void);
00076
00083
        int setDriveCurrent(u int8 t current);
00084
00091
        int setHoldCurrent(u_int8_t current);
00092
00098
        int setBrakeMode(u_int8_t mode);
00099
00105
        int getStall(u_int8_t &stall);
00106
00111
        int enableStallguard(u_int8_t sensitivity);
00112
00118
        int getIsHomed(u_int8_t &homed);
00119
00126
        int getIsHomed(void);
00127
00134
        bool isHomed(void);
00135
00141
        int getIsSetup(u_int8_t &setup);
00142
00147
        int getIsSetup(void);
00148
00152
        bool isSetup(void);
00153
00154
        int moveSteps(int32_t steps);
00155
        int checkCom(void);
00156
        u_int8_t getFlags(void);
00161
00162
00163
        std::string name;
00164
00165 protected:
00166 private:
00176
        enum stp_reg_t
00177
00178
          PING = 0x0f,
          SETUP = 0x10,
SETRPM = 0x11,
00179
00180
          GETDRIVERRPM = 0x12,
00181
00182
          MOVESTEPS = 0x13,
MOVEANGLE = 0x14,
00183
00184
          MOVETOANGLE = 0x15,
00185
           GETMOTORSTATE = 0 \times 16,
00186
           RUNCOTINOUS = 0x17,
          ANGLEMOVED = 0x18,
SETCURRENT = 0x19,
00187
00188
          SETHOLDCURRENT = 0x1A,
SETMAXACCELERATION = 0x1B,
00189
00190
00191
           SETMAXDECELERATION = 0x1C,
00192
           SETMAXVELOCITY = 0x1D,
00193
          ENABLESTALLGUARD = 0x1E
00194
          DISABLESTALLGUARD = 0x1F,
          CLEARSTALL = 0x20,
ISSTALLED = 0x21,
00195
00196
           SETBRAKEMODE = 0x22,
00197
          ENABLEPID = 0x23,
DISABLEPID = 0x24,
00198
00199
00200
           ENABLECLOSEDLOOP = 0x25,
          DISABLECLOSEDLOOP = 0x26,
00201
00202
          SETCONTROLTHRESHOLD = 0x27,
00203
           MOVETOEND = 0x28,
00204
           STOP = 0x29,
00205
           GETPIDERROR = 0x2A,
00206
           CHECKORIENTATION = 0x2B,
00207
           GETENCODERRPM = 0x2C
00208
          HOME = 0 \times 2D.
00209
           ISHOMED = 0 \times 2E,
00210
           ISSETUP = 0x2F
00211
00212
00213
        template <typename T>
        int read(const stp_reg_t reg, T &data, u_int8_t &flags);
00214
00215
```

```
00216
        template <typename T>
00217
       int write(const stp_reg_t reg, T data, u_int8_t &flags);
00218
00237
       u_int8_t flags = 0x00;
00238
00239
       u_int8_t ishomed = 0;
00240 u_int8_t issetup = 0;
00241
00242
       int address;
       float gearRatio = 1;
int offset = 0;
00243
00244
00245
00246
       int handle = -1;
00247 };
00248
00249 #include "joint_communication/mJoint.hpp"
00250
00251 #endif
```


6.13 ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication/mJoint.hpp File Reference

Templated functions for the Joint class.

```
#include "joint_communication/mJoint.h"
#include "joint_communication/uI2C.h"
#include "joint_communication/common.h"
Include dependency graph for mJoint.hpp:
```



This graph shows which files directly or indirectly include this file:



6.13.1 Detailed Description

Templated functions for the Joint class.

Author

Sebastian Storz

Version

0.1

Date

2025-05-29

Copyright

Copyright (c) 2025

This header must be included at the END of the mJoint.h file.

6.14 mJoint.hpp 59

6.14 mJoint.hpp

Go to the documentation of this file.


```
00012 #include "joint_communication/mJoint.h" 00013 #include "joint_communication/uI2C.h"
00014 #include "joint_communication/common.h"
00031 template <typename T>
00032 int Joint::read(const stp_reg_t reg, T &data, u_int8_t &flags)
00033 {
           size_t size = sizeof(T) + RFLAGS_SIZE;
00034
           char *buf = new char[size];
           int n = readFromI2CDev(this->handle, reg, buf, size);
00037
           if (n != static_cast<int>(size))
00038
00039
                delete[] buf;
00040
                return -1:
00041
           memcpy(&data, buf, size - RFLAGS_SIZE);
memcpy(&flags, buf + size - RFLAGS_SIZE, RFLAGS_SIZE);
00042
00043
00044
           delete[] buf;
00045
           return 0;
00046 }
00047
00063 template <typename T>
00064 int Joint::write(const stp_reg_t reg, T data, u_int8_t &flags)
00065 {
00066
           size_t size = sizeof(T) + RFLAGS_SIZE;
           char *buf = new char[size];
memcpy(buf, &data, size - RFLAGS_SIZE);
int rc = writeToI2CDev(this->handle, reg, buf, size - RFLAGS_SIZE, buf + size - RFLAGS_SIZE);
00067
00068
00069
00070
           rc = rc > 0 ? 0 : rc;
00071
00072
           memcpy(&flags, buf + size - RFLAGS_SIZE, RFLAGS_SIZE);
00073
           delete[] buf;
00074
           return rc;
00075 }
```

6.15 ROS2/ros2_scara_ws/src/joint_communication/include/joint_← communication/mJointCom.h File Reference


File containing the Joint_comms class.

```
#include <vector>
#include <iostream>
#include "joint_communication/mJoint.h"
```

Include dependency graph for mJointCom.h:



This graph shows which files directly or indirectly include this file:



Classes

· class Joint_comms

Communication object for all joints.

6.15.1 Detailed Description

File containing the Joint_comms class.

6.16 mJointCom.h 61

Author

Sebastian Storz

Version

0.1

Date

2025-05-27

Copyright

Copyright (c) 2025

Include this file for API functions to interact with the stepper motors.

6.16 mJointCom.h

Go to the documentation of this file.

```
00001
00014 #ifndef MJOINTCOM H
00015 #define MJOINTCOM H
00016
00017 #include <vector>
00018 #include <iostream>
00019 #include "joint_communication/mJoint.h"
00020
00027 class Joint comms
00028 {
00029 public:
00030
      Joint_comms(void);
00031
        ~Joint_comms();
00032
00041
       int init (void);
00042
00050
       int deinit (void);
00051
00068
        void addJoint(const int address, const std::string name, const float gearRatio, const int offset);
00069
00083
        int enables(std::vector<u_int8_t> driveCurrent_v, std::vector<u_int8_t> holdCurrent_v);
00084
00093
        int enables(u_int8_t driveCurrent, u_int8_t holdCurrent);
00094
00101
00102
00117
        int home(std::string name, u_int8_t direction, u_int8_t rpm, int8_t sensitivity, u_int8_t current);
00118
00128
        int getPositions(std::vector<float> &angle_v);
00129
00139
        int setPositions(std::vector<float> angle_v);
00140
00150
        int getVelocities(std::vector<float> &degps_v);
00151
00161
        int setVelocities(std::vector<float> degps v);
00162
00175
        int checkOrientations(std::vector<float> angle_v);
00176
        int checkOrientations(float angle = 10.0);
00182
00183
00191
        int stops (bool mode);
00192
00197
        int disableCLs(void);
00198
00207
        int setDriveCurrents(std::vector<u_int8_t> current);
00208
00216
        int setDriveCurrents(u int8 t current);
00217
00225
        int setHoldCurrents(std::vector<u_int8_t> current);
```


```
00226
00234
       int setHoldCurrents(u_int8_t current);
00235
00243
       int setBrakeModes(u_int8_t mode);
00244
00252
       int enableStallquards(std::vector<u_int8_t> thresholds);
00259
       std::vector<Joint> joints;
00260
00261 protected:
00262 private:
00263 };
00264
00265 #endif
```

6.17 ROS2/ros2_scara_ws/src/joint_communication/include/joint_← communication/ul2C.h File Reference


Low level utility for I2C communication on Raspberry Pi using Igpio library.

```
#include <cstring>
#include <errno.h>
#include <fcntl.h>
#include <iostream>
#include <termios.h>
#include <unistd.h>
```

Include dependency graph for uI2C.h:



This graph shows which files directly or indirectly include this file:



Macros

- #define ACK 'O'
- #define NACK 'N'
- #define RFLAGS_SIZE 1

Size of the return flags in bytes.

• #define MAX_BUFFER 4

Maximum size of I2C Payload in bytes.

Functions

- int openI2CDevHandle (const int dev addr)
 - Initiates an I2C device on the bus.
- int readFromI2CDev (const int dev_handle, const int reg, char *buffer, const int data_length)
 reads block of bytes from device to buffer
- int writeTol2CDev (const int dev_handle, const int reg, char *tx_buffer, const int data_length, char *RFLAGS buffer)

writes block of bytes from buffer to device

• int closel2CDevHandle (const int dev_handle)

close an I2C device on the bus

6.17.1 Detailed Description

Low level utility for I2C communication on Raspberry Pi using Igpio library.

Author

Sebastian Storz

Version

0.1

Date

2025-05-28

Copyright

Copyright (c) 2025

Igpio needs to be installed and linked! Installation:

```
cd ~
sudo apt update
sudo apt install -y swig
wget https://github.com/joan2937/lg/archive/master.zip
unzip master.zip
cd lg-master
make
sudo make install
cd ..
sudo rm -rf lg-master
rm master.zip
```

bash

6.17.2 Macro Definition Documentation

6.17.2.1 ACK

```
#define ACK 'O'
```

6.17.2.2 MAX_BUFFER

```
#define MAX_BUFFER 4
```

Maximum size of I2C Payload in bytes.

4 bytes used to transmit floats and int32_t

6.17.2.3 NACK

```
#define NACK 'N'
```

6.17.2.4 RFLAGS_SIZE

```
#define RFLAGS_SIZE 1
```

Size of the return flags in bytes.

Only one byte used and hence set to 1.

6.17.3 Function Documentation

6.17.3.1 closel2CDevHandle()

close an I2C device on the bus

Parameters

Returns

0 on OK, negative on error.

6.17.3.2 openI2CDevHandle()

```
int openI2CDevHandle ( {\tt const\ int}\ {\it dev\_addr}\ )
```

Initiates an I2C device on the bus.

Parameters

dev_addr	7-bit device adress [0 - 0x7F]

Returns

the device handle, negative on error.

6.17.3.3 readFromI2CDev()

reads block of bytes from device to buffer

Parameters

dev_handle	device handle obtained from openI2CDevHandle
reg	the command/data register
buffer	pointer to data buffer to hold received values
data_length	number of bytes to read

Returns

number of bytes read, negative on error.

6.17.3.4 writeToI2CDev()

writes block of bytes from buffer to device

Parameters

dev_handle	device handle obtained from openI2CDevHandle
reg	the command/data register
tx_buffer	pointer to data buffer holding the data to send
data_length	number of bytes to send
RFLAGS_buffer	buffer to hold returned flags

Returns

0 on OK, negative on error.

6.18 ul2C.h

Go to the documentation of this file.


```
00001
00028 #ifndef USERIAL_H
00029 #define USERIAL_H
00030 #include <cstring>
00031 #include <fcntl.h>
00032 #include <fcntl.h>
00033 #include <iostream>
00034 #include <termios.h>
00035 #include <turnios.h>
00036
00037 #define ACK 'O'
00038 #define NACK 'N'
00039
00043 #define RFLAGS_SIZE 1
00044
00048 #define MAX_BUFFER 4 // Bytes
00049
00055 int openI2CDevHandle(const int dev_addr);
```

6.19 ROS2/ros2_scara_ws/src/joint_communication/include/joint_← communication/uPWM.h File Reference


Includes source code for Hardware PWM generation on Raspberry Pi 4.

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <unistd.h>
#include <string>
#include <iostream>
#include <math.h>
```

Include dependency graph for uPWM.h:



This graph shows which files directly or indirectly include this file:



Classes

class RPI_PWM

PWM class for the Raspberry PI 4 and 5.

6.19.1 Detailed Description

Includes source code for Hardware PWM generation on Raspberry Pi 4.

Author

Sebastian Storz and Bernd Porr, bernd.porr@glasgow.ac.uk

Version

0.1

Date

2025-05-27

Igpio, the library used for I2C access can only generate soft PWM, The timing jitter will cause the servo to fidget. This may cause it to overheat and wear out prematurely.

Copyright

Copyright (c) 2025

6.20 uPWM.h

6.20 uPWM.h

Go to the documentation of this file.


```
00001
00019 #ifndef __RPIPWM
00020 #define __RPIPWM
00021
00022 #include <stdio.h>
00023 #include <stdlib.h>
00024 #include <string.h>
00025 #include <unistd.h>
00026 #include <string>
00027 #include <iostream>
00028 #include <math.h>
00029
00033 class RPI_PWM
00034 {
00035 public:
00044
          int start (int channel, int frequency, float duty_cycle = 0, int chip = 2)
00045
00046
               chippath = "/sys/class/pwm/pwmchip" + std::to_string(chip);
               pwmpath = chippath + "/pwm" + std::to_string(channel);
std::string p = chippath + "/export";
FILE *const fp = fopen(p.c_str(), "w");
if (NULL == fp)
00047
00048
00049
00050
00051
               {
                   std::cerr « "PWM device does not exist. Make sure to add 'dtoverlay=pwm-2chan' to
      /boot/firmware/config.txt.\n";
00053
                  return -1;
00054
00055
               const int r = fprintf(fp, "%d", channel);
00056
               fclose(fp);
00057
               if (r < 0)
00058
                   return r;
               usleep(100000); // it takes a while till the PWM subdir is created
00059
               per = (int)1E9 / frequency;
setPeriod(per);
00060
00061
00062
               setDutyCycle(duty_cycle);
00063
               enable();
00064
               return r;
00065
          }
00066
00070
          void stop()
00071
00072
               disable();
00073
00074
00075
          ~RPI_PWM()
00076
           {
00077
               disable();
00078
          }
00079
00085
          inline int setDutyCycle(float v) const
00086
              const int dc = (int)round((float)per * (v / 100.0));
const int r = setDutyCycleNS(dc);
00087
00088
00089
               return r;
00090
00091
00092 private:
00093
          void setPeriod(int ns) const
00094
               writeSYS(pwmpath + "/" + "period", ns);
00096
00097
00098
           inline int setDutyCycleNS(int ns) const
00099
               const int r = writeSYS(pwmpath + "/" + "duty_cycle", ns);
00100
00101
               return r;
00102
          }
00103
00104
          void enable() const
00105
               writeSYS(pwmpath + "/" + "enable", 1);
00106
00107
          }
00108
00109
          void disable() const
00110
           {
               writeSYS(pwmpath + "/" + "enable", 0);
00111
00112
00113
00114
          int per = 0;
00115
00116
           std::string chippath;
00117
          std::string pwmpath;
```

```
00119
          inline int writeSYS(std::string filename, int value) const
00120
              FILE *const fp = fopen(filename.c_str(), "w");
00121
00122
              if (NULL == fp)
00123
00124
                  return -1;
00125
00126
              const int r = fprintf(fp, "%d", value);
00127
              fclose(fp);
00128
              return r;
00129
00130 };
00131
00132 #endif
```

6.21 ROS2/ros2_scara_ws/src/joint_communication/src/joint_comm_← node.cpp File Reference

```
#include <signal.h>
#include <unistd.h>
#include "joint_communication/mJointCom.h"
#include "joint_communication/mGripper.h"
#include <cmath>
```

Include dependency graph for joint_comm_node.cpp:



Functions

- void INT handler (int s)
- int main (int argc, char **argv)

Variables

- · Joint_comms _Joints
- Gripper _Gripper

6.21.1 Function Documentation

6.21.1.1 INT_handler()

```
void INT_handler ( \quad \text{int } s \ )
```

6.21.1.2 main()

```
int main (
          int argc,
          char ** argv )
```

6.21.2 Variable Documentation

6.21.2.1 _Gripper


Gripper _Gripper

6.21.2.2 _Joints

Joint_comms _Joints


6.22 ROS2/ros2_scara_ws/src/joint_communication/src/mGripper.cpp File Reference

#include "joint_communication/mGripper.h"
Include dependency graph for mGripper.cpp:



6.23 ROS2/ros2_scara_ws/src/joint_communication/src/mJoint.cpp File Reference


#include "joint_communication/uI2C.h"
#include "joint_communication/mJoint.h"
Include dependency graph for mJoint.cpp:



6.24 ROS2/ros2_scara_ws/src/joint_communication/src/mJointCom.cpp File Reference

#include "joint_communication/uI2C.h"
#include "joint_communication/mJointCom.h"


Include dependency graph for mJointCom.cpp:



6.25 ROS2/ros2_scara_ws/src/joint_communication/src/ul2C.cpp File Reference

```
#include "joint_communication/uI2C.h"
#include "joint_communication/common.h"
#include <lgpio.h>
```

Include dependency graph for uI2C.cpp:



Functions

int openI2CDevHandle (const int dev_addr)

Initiates an I2C device on the bus.

• int readFromI2CDev (const int dev_handle, const int reg, char *buffer, const int data_length)

reads block of bytes from device to buffer

• int writeToI2CDev (const int dev_handle, const int reg, char *tx_buffer, const int data_length, char *RFLAGS_buffer)

writes block of bytes from buffer to device

• int closel2CDevHandle (const int dev_handle)

close an I2C device on the bus

6.25.1 Function Documentation

6.25.1.1 closel2CDevHandle()

close an I2C device on the bus

Parameters

Returns

0 on OK, negative on error.

6.25.1.2 openI2CDevHandle()

Initiates an I2C device on the bus.

Parameters

```
dev_addr 7-bit device adress [0 - 0x7F]
```

Returns

the device handle, negative on error.

6.25.1.3 readFromI2CDev()

```
char * buffer,
const int data_length )
```

reads block of bytes from device to buffer

Parameters

dev_handle	device handle obtained from openI2CDevHandle
reg	the command/data register
buffer	pointer to data buffer to hold received values
data_length	number of bytes to read

Returns

number of bytes read, negative on error.

6.25.1.4 writeToI2CDev()

writes block of bytes from buffer to device

Parameters

dev_handle	device handle obtained from openI2CDevHandle
reg	the command/data register
tx_buffer	pointer to data buffer holding the data to send
data_length	number of bytes to send
RFLAGS_buffer	buffer to hold returned flags

Returns

0 on OK, negative on error.

Index

```
Gripper
                                                           Gripper, 10
                                                           Joint, 15
    joint_comm_node.cpp, 71
_Joints
                                                           Joint comms, 26
    joint_comm_node.cpp, 71
                                                      disable
\sim\!\!\text{Joint\_comms}
                                                           Gripper, 10
    Joint_comms, 25
                                                           Joint, 15
\simRPI PWM
                                                           RPI PWM, 34
    RPI PWM, 34
                                                      disableCL
                                                           Joint, 15
ACK
                                                      DISABLECLOSEDLOOP
    joint.h, 41
                                                           Joint, 14
    ul2C.h, 64
                                                           joint.h, 43
addJoint
                                                      disableCLs
    Joint comms, 25
                                                           Joint_comms, 26
address
                                                      DISABLEPID
    Joint, 22
                                                           Joint, 14
ADR
                                                           joint.h, 43
    configuration.h, 38
                                                      disables
ANGLEMOVED
                                                           Joint comms, 27
    Joint, 14
                                                      DISABLESTALLGUARD
    joint.h, 42
                                                           Joint, 14
Arduino/joint/configuration.h, 37, 39
                                                           joint.h, 43
Arduino/joint/joint.h, 39, 44
                                                      docs/DOCS README.md, 49
Arduino/joint/joint.ino, 45
                                                      Documentation, 1
                                                      DUMP_BUFFER
checkCom
                                                           common.h, 51
    Joint, 15
                                                           joint.h, 41
CHECKORIENTATION
    Joint, 14
                                                      enable
    joint.h, 43
                                                           Gripper, 10
checkOrientation
                                                           Joint, 15
    Joint, 15
                                                           RPI_PWM, 34
checkOrientations
                                                      ENABLECLOSEDLOOP
    Joint_comms, 26
                                                           Joint, 14
chippath
                                                           joint.h, 43
    RPI PWM, 35
                                                      ENABLEPID
CLEARSTALL
                                                           Joint, 14
    Joint, 14
                                                           joint.h, 43
    joint.h, 43
                                                      enables
closeI2CDevHandle
                                                           Joint_comms, 27
    ul2C.cpp, 74
                                                      ENABLESTALLGUARD
    ul2C.h, 65
                                                           Joint, 14
common.h
                                                           joint.h, 42
    DUMP_BUFFER, 51
                                                      enableStallguard
configuration.h
                                                           Joint. 16
    ADR, 38
                                                      enableStallguards
    MAXACCEL, 38
                                                           Joint_comms, 28
    MAXVEL, 38
                                                      ENCODER2JOINTANGLE
                                                           mJoint.h, 55
deinit
```

flags	joint.h, 43
Joint, 22	isHomed
D. 1	Joint, 18
gearRatio	ishomed
Joint, 23	Joint, 23
GETDRIVERRPM	ISSETUP
Joint, 14	Joint, 14
joint.h, 42 GETENCODERRPM	joint.h, 43
	isSetup
Joint, 14 joint.h, 43	Joint, 19
getFlags	issetup
Joint, 16	Joint, 23
getIsHomed	ISSTALLED
Joint, 16	Joint, 14
getIsSetup	joint.h, 43
Joint, 17	J4
GETMOTORSTATE	joint.ino, 46
Joint, 14	Joint, 12
joint.h, 42	address, 22
GETPIDERROR	ANGLEMOVED, 14
Joint, 14	checkCom, 15
joint.h, 43	CHECKORIENTATION, 14
getPosition	checkOrientation, 15
Joint, 17	CLEARSTALL, 14
getPositions	deinit, 15
Joint_comms, 28	disable, 15
getStall	disableCL, 15
Joint, 17	DISABLECLOSEDLOOP, 14
getVelocities	DISABLEPID, 14
Joint_comms, 28	DISABLESTALLGUARD, 14
getVelocity	enable, 15
Joint, 18	ENABLECLOSEDLOOP, 14
Gripper, 9	ENABLEPID, 14
deinit, 10	ENABLESTALLGUARD, 14
disable, 10	enableStallguard, 16
enable, 10	flags, 22
Gripper, 10	gearRatio, 23
init, 11	GETDRIVERRPM, 14
pwm, 11	GETENCODERRPM, 14
setPosition, 11	getFlags, 16
	getIsHomed, 16
handle	getIsSetup, 17
Joint, 23	GETMOTORSTATE, 14
HOME	GETPIDERROR, 14
Joint, 14	getPosition, 17
joint.h, 43	getStall, 17
home	getVelocity, 18
Joint, 18	handle, 23
Joint_comms, 29	HOME, 14
init	home, 18
Gripper, 11	init, 18
Joint, 18	ISHOMED, 14
Joint_comms, 29	isHomed, 18
INT handler	ishomed, 23
joint_comm_node.cpp, 70	ISSETUP, 14
ISHOMED	isSetup, 19
Joint, 14	issetup, 23
30mg 11	ISSTALLED, 14

Joint, 15	RFLAGS_SIZE, 42
MOVEANGLE, 14	RUNCOTINOUS, 42
MOVESTEPS, 14	SETBRAKEMODE, 43
moveSteps, 19	SETCONTROLTHRESHOLD, 43
MOVETOANGLE, 14	SETCURRENT, 42
MOVETOEND, 14	SETHOLDCURRENT, 42
name, 23	SETMAXACCELERATION, 42
offset, 23	SETMAXDECELERATION, 42
PING, 14	SETMAXVELOCITY, 42
printInfo, 19	SETRPM, 42
read, 19	SETUP, 42
RUNCOTINOUS, 14	STOP, 43
SETBRAKEMODE, 14	stp_reg_t, 42
setBrakeMode, 20	writeValue, 43
SETCONTROLTHRESHOLD, 14	
	joint.ino
SETCURRENT, 14	J4, 46
setDriveCurrent, 20	loop, 47
SETHOLDCURRENT, 14	receiveEvent, 47
setHoldCurrent, 20	reg, 48
SETMAXACCELERATION, 14	requestEvent, 47
SETMAXDECELERATION, 14	rx_buf, 48
SETMAXVELOCITY, 14	rx_data_ready, 49
setPosition, 21	rx_length, 49
SETRPM, 14	setup, 47
SETUP, 14	stepper, 49
setVelocity, 21	stepper_receive_handler, 48
STOP, 14	stepper_request_handler, 48
stop, 21	tx_buf, 49
stp_reg_t, 14	tx_data_ready, 49
write, 21	tx_length, 49
joint.h	JOINT2ENCODERANGLE
ACK, 41	mJoint.h, 55
ANGLEMOVED, 42	joint_comm_node.cpp
CHECKORIENTATION, 43	_Gripper, 71
CLEARSTALL, 43	_Joints, 71
DISABLECLOSEDLOOP, 43	INT handler, 70
DISABLEPID, 43	main, 70
DISABLESTALLGUARD, 43	Joint_comms, 24
DUMP_BUFFER, 41	~Joint comms, 25
ENABLECLOSEDLOOP, 43	addJoint, 25
ENABLEPID, 43	checkOrientations, 26
ENABLESTALLGUARD, 42	deinit, 26
GETDRIVERRPM, 42	disableCLs, 26
GETENCODERRPM, 43	disables, 27
GETMOTORSTATE, 42	enables, 27
GETPIDERROR, 43	enableStallguards, 28
HOME, 43	getPositions, 28
ISHOMED, 43	getVelocities, 28
ISSETUP, 43	home, 29
ISSTALLED, 43	
	init, 29
MAX_BUFFER, 42	Joint_comms, 25
MOVESTERS 42	joints, 33
MOVESTEPS, 42	setBrakeModes, 30
MOVETOANGLE, 42	setDriveCurrents, 30
MOVETOEND, 43	setHoldCurrents, 31
NACK, 42	setPositions, 32
PING, 42	setVelocities, 32
readValue, 43	stops, 32

tatasa	::100 ann 74
joints	ul2C.cpp, 74
Joint_comms, 33	ul2C.h, 65
	readValue
loop	joint.h, 43
joint.ino, 47	receiveEvent
	joint.ino, 47
main	•
joint_comm_node.cpp, 70	reg
MAX BUFFER	joint.ino, 48
joint.h, 42	requestEvent
	joint.ino, 47
ul2C.h, 64	RFLAGS_SIZE
MAXACCEL	joint.h, 42
configuration.h, 38	ul2C.h, 64
MAXVEL	
configuration.h, 38	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
mJoint.h	49, 51
ENCODER2JOINTANGLE, 55	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
	51, 53
JOINT2ENCODERANGLE, 55	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
MOVEANGLE	53, 55
Joint, 14	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
joint.h, 42	
MOVESTEPS	57, 59
Joint, 14	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
·	59, 61
joint.h, 42	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
moveSteps	62, 66
Joint, 19	ROS2/ros2_scara_ws/src/joint_communication/include/joint_communication
MOVETOANGLE	67, 69
Joint, 14	
joint.h, 42	ROS2/ros2_scara_ws/src/joint_communication/src/joint_comm_node.cpp,
MOVETOEND	70
	ROS2/ros2_scara_ws/src/joint_communication/src/mGripper.cpp,
Joint, 14	71
joint.h, 43	ROS2/ros2_scara_ws/src/joint_communication/src/mJoint.cpp,
NACK	72
NACK	ROS2/ros2_scara_ws/src/joint_communication/src/mJointCom.cpp,
joint.h, 42	
ul2C.h, 64	72
name	ROS2/ros2_scara_ws/src/joint_communication/src/ul2C.cpp,
Joint, 23	73
	RPI_PWM, 33
offset	\sim RPI_PWM, 34
Joint, 23	chippath, 35
	disable, 34
openI2CDevHandle	
ul2C.cpp, 74	enable, 34
ul2C.h, 65	per, 35
	pwmpath, 35
per	setDutyCycle, 34
RPI PWM, 35	setDutyCycleNS, 34
PING	setPeriod, 34
Joint, 14	start, 34
joint.h, 42	
-	stop, 35
printInfo	writeSYS, 35
Joint, 19	RUNCOTINOUS
pwm	Joint, 14
Gripper, 11	joint.h, 42
pwmpath	rx_buf
RPI_PWM, 35	joint.ino, 48
······, ••	•
read	rx_data_ready
Joint, 19	joint.ino, 49
	rx_length
readFromI2CDev	

joint.ino, 49	RPI PWM, 34
•	stepper
SETBRAKEMODE	joint.ino, 49
Joint, 14	stepper_receive_handler
joint.h, 43	joint.ino, 48
setBrakeMode	stepper_request_handler
Joint, 20 setBrakeModes	joint.ino, 48
Joint_comms, 30	STOP
SETCONTROLTHRESHOLD	Joint, 14
Joint, 14	joint.h, 43
joint.h, 43	stop Joint, <mark>21</mark>
SETCURRENT	RPI PWM, 35
Joint, 14	stops
joint.h, 42	Joint_comms, 32
setDriveCurrent	stp_reg_t
Joint, 20	Joint, 14
setDriveCurrents	joint.h, 42
Joint_comms, 30	
setDutyCycle	Todo List, 3
RPI_PWM, 34	tx_buf
setDutyCycleNS RPI_PWM, 34	joint.ino, 49
SETHOLDCURRENT	tx_data_ready
Joint, 14	joint.ino, 49 tx_length
joint.h, 42	joint.ino, 49
setHoldCurrent	joint.ino, 40
Joint, 20	ul2C.cpp
setHoldCurrents	closeI2CDevHandle, 74
Joint_comms, 31	openI2CDevHandle, 74
SETMAXACCELERATION	readFromI2CDev, 74
Joint, 14	writeToI2CDev, 76
joint.h, 42	ul2C.h
SETMAXDECELERATION	ACK, 64
Joint, 14	closel2CDevHandle, 65
joint.h, 42 SETMAXVELOCITY	MAX_BUFFER, 64 NACK, 64
Joint, 14	openI2CDevHandle, 65
joint.h, 42	readFromI2CDev, 65
setPeriod	RFLAGS SIZE, 64
RPI PWM, 34	writeToI2CDev, 66
setPosition	
Gripper, 11	write
Joint, 21	Joint, 21
setPositions	writeSYS
Joint_comms, 32	RPI_PWM, 35 writeToI2CDev
SETRPM	ul2C.cpp, 76
Joint, 14	ul2C.h, 66
joint.h, 42 SETUP	writeValue
Joint, 14	joint.h, 43
joint.h, 42	J , -
setup	
joint.ino, 47	
setVelocities	
Joint_comms, 32	
setVelocity	
Joint, 21	
start	